Application Variables

Last Modified on 07/10/2024 9:42 am EDT

Starting with V10.0, Cora SeQuence has been renamed to Cora Orchestration.

Overview

Following is the list of the application variables available in Cora SeQuence. For these application variables, a key and its value is defined in the Application Variables table on Admin console, and the key is then used in Cora SeQuence expressions.

For details, see the this article.

Different application variables are defined in the system for different settings explained in the below sections.

Organizational settings

Key	Type	Description	Value	Version
Administration.Instrumentation.Ex ternalToolName	Text	Enables you to add the name of the third-party tool you want to use to view logs. By default, the EventViewer opens the logs in Cora Orchestration.	Third-party tool name For example, DataDog	10.3
Administration.Instrumentation.Ex ternalToolUrl	Text	Enables you to set the URL of the third-party tool you want to use to view logs.	Tool URL (that will open in a new tab in browser)	10.3
Administration.Organization.Tree. PageSize	Numeri c/Integ er	Specifies the number of: • Groups displayed by default • Groups that load when user clicks Load more	 20 (default) 0: displays all groups, without "Load more" 	9.0-10.x
Administration.Organization.Tree. Visible	Boolea n	Hides or shows the organizational structure on the Organization Management page.	True (default)False	9.0-10.x

Key	Туре	Description	Value	Version
Administration.Ribbon.Environmen tColor	Text	Enables you to customize the color of the Administration ribbon. For details, see the Differentiate Cora SeQuence environments with color enhancement in the Cora SeQuence 8.6.1 Release Notes.	ed7b87	8.6.1- 10.x
Administration.Ribbon.Environmen tText	Text	Enables you to add custom text to the Administration ribbon. For details, see the Differentiate Cora SeQuence environments with color enhancement in the Cora SeQuence 8.6.1 Release Notes.	Dev	8.6.1- 10.x

Background Runtime Service

These application variables determine batch size, number of instances in batches, and the delay after which aborted instances are moved to closed tables.

For details, see this article.

Key	Туре	Description	Value	Version
BRS.MoveToClosed.AbortedWork flowInstancesRetentionDelayInDa ys	Numeric /Integer	Delay in moving aborted instances to closed tables.	7 (default)	9.5-10.x
BRS.MoveToClosed.BatchSize	Numeric /Integer	Determines the number of instances that are moved in every batch.	100 (default)	9.0- 10.x
BRS.MoveToClosed.NumberOfBat chesInOneCycle	Numeric /Integer	Maximum number of batches that run in a single service cycle run.	10 (default)	9.0- 10.x

Job Execution Services (JES)

These variable determine various settings defined through JES. For details, see this article.

Key	Туре	Description	Value	Version
JES.EmailSender.DelaySendOfMe ssagesInQueueBySeconds	Numeric /Integer	Delay the email send out time. NOTE Decimal values are not allowed.	0-30 sec	10.5

Case management settings

Key	Type	Description	Value	Version
Portal.HotOperations.GroupListWidth	Numeri c/Integ er	Maximum width of a combo box.	400px (default)	10.4
Portal.HotOperations.GroupPathL ength	Numeri c/Integ er	Maximum number of characters that will appear in a drop down.	n (no max limit)	10.4
Portal.HotOperations.HideDefault Dashboards	Boolean	Hides or shows the default dashboards in the portal.	 True (default) - to show the default dashboards False - to hide the default dashboards 	10.3.1
Portal.HotOperations.TeamLeader .MaxSelectionSize	Numeri c/Integ er	Maximum number of tasks that can be selected for multiple actions to be performed in the Team Leader tasks list	25 (default)100 (maximum)	9.7.2- 10.x
Portal.HotOperations.OpsManage r.MaxSelectionSize	Numeri c/Integ er	Maximum number of cases that can be selected for multiple actions to be performed in the Operation Manager cases list	25 (default)100 (maximum)	9.7.2- 10.x

Key	Type	Description	Value	Version
Portal.HotOperations.Board.Show BucketNumberOfCases	Boolean	Hides or shows the number of cases per allocation work bucket in the HotOperations Work Allocation Board for Operations Managers. For details, see this article.	 True (default) - to show the property False - to hide the property 	9.2-10.
Portal.HotOperations.Board.Show BucketCost	Boolean	Hides or shows the Cost Per Person field in the HotOperations Work Allocation Board for Operations Managers. For details, see this article.	 True (default) - to show the field False - to hide the field 	9.2-10.>
Portal.HotOperations.Grid.TileTe mplate.OpsManager Portal.HotOperations.Grid.Expand edTileTemplate.OpsManager Portal.HotOperations.Grid.TileTemplate.TeamLeader	Text	Prevents losing any changes made to the tile display templates on system upgrade. For details, see this article.	Path to the file location. For example, the path to the template of the Team Member grid: [rootfolder]\Cora	9.2-10.>
Portal.HotOperations.Grid.Expand edTileTemplate.TeamLeader Portal.HotOperations.Grid.TileTe mplate.TeamMember Portal.HotOperations.Grid.Expand edTileTemplate.TeamMember			SeQuence\Flowtim e\Shared Resources\Compon ents\HotOperation s\Flowtime\Templ ates\TeamMember \MYgrid-tile.html	
Portal.HotOperations.TeamMemb er.SolutionsMenuId	Text	Determines the menu to which the solutions' task list will be added.	Menu Id	9.2-9.x
Portal.HotOperations.TeamMemb er.DefaultPage	Text	Determines the Team Member's default task list page of a solution under My Tasks.	URL	9.2-9.x

Key	Type	Description	Value	Version
Portal.HotOperations.TeamMemb er.EnableGroupFilter	Boolean	Enables the Team Filter feature for Team Members, thus allowing them to filter their tasks by team.	• True • False	9.1-10.x
Portal.HotOperations.TeamLeader .EnableSetImportance	Boolean	Enables the Team Leaders to change the Task importance.	TrueFalse (default)	8.7-10.x
Portal.HotOperations.TeamMemb er.EnableSetImportance	Boolean	Enables the Team Members to change the Task importance.	TrueFalse (default)	8.7-10.>
Portal.HotOperations.Board.Buck etTileTemplate.OpsManager	Text	Enables the Operations Manager to customize the data and style that displays to HotOperations users by modifying default.html file. For details, see this article.	~/Shared Resources/Compon ents/HotOperation s/Flowtime/Templ ates/OpsManager/ default.html (default)	8.6-10.
Portal.HotOperations.Board.Buck etTileTemplate.TeamLeader	Text	Enables the Team Leader to customize the data and style that displays to HotOperations users by modifying default.html file. For details, see this article.	~/Shared Resources/Compon ents/HotOperation s/Flowtime/Templ ates/TeamLeader/d efault.html (default)	8.6-10.
Portal.HotOperations.Board.Show BucketCost	Boolean	Hides or shows the Cost Per Person in the HotOperations Work Allocation board for Operations Managers. For details, see this article.	 True (default) - to show this property False - to hide this property 	8.7-10.>

Key	Туре	Description	Value	Version
Portal.HotOperations.Board.Show BucketUtilization	Boolean	Hides or shows the Workload in the HotOperations Work Allocation board for Operations Managers. For details, see this article.	 True (default) - to show this property False - to hide this property 	8.7-10.x
Portal.HotOperations.Board.Team Leader.DefaultView	Text	Enables focused view for Team Leader Dashboard	• All • Focused	8.6-10.x
Portal.HotOperations.OpsManage r.DefaultPage	Text	Enables the Operations Manager to set the HotOperations default page to a custom page of their choice. For details, see this article.	~/HotOperations/O psManager/CasesLi st.aspx	8.6-9.x
Portal.HotOperations.TeamLeader .DefaultPage	Text	Enables the Team Leader to set the HotOperations default page to a custom page of their choice. For details, see this article.	~/HotOperations/O psManager/TaskLis t.aspx	8.6-9.x

Portal settings

Key	Туре	Description	Value	Version
Forms.Controls.FileUploadMaxSiz eBytes	Numeri c/Integ er	Enables the user to check the max file size allowed to be uploaded. This limit is checked after the file is selected and before the file upload is started by the form controls FileUpload, AsyncFileUpload, AttachmentsView.	• n • Default: 20,480,000 (20 MB) If value is 0 or he unlimited.	10.6

Key	Type	Description	Value	Version
Portal.Components.ShowRecentW orkItems	Boolea n	Enables the user to search and view recent work items in the portal, and search a case with case title.	True (default)False	10.6
Portal.Components.Grid.DefaultOpenAction	Text	Sets the operation to be performed on clicking a task in a grid.	OpenAndFetc h (default)Open	10.5
Portal. Default Process Page Guid	Text	Sets the sub menu that correlates to the workflow space guid as the default process page.	WorkflowSpace guid	10.5
Portal.Forms.Topbar.ShowMenu	Boolea n	Enables the user to hide or show the vertical ellipsis menu from the top bar of the case details page	True (default)False	10.5
Portal.Substitution	Boolea n	Enables substitution functionality for users to set substitute user(s) for themselves.	TrueFalse (default)	10.4.1
Portal.Substitution.Roles	Text	Sets the roles, members of which can add and enable substitute users for other members of their team.	List of roles Default is Group Manager, Team Leader.	10.4.1
Portal.Components.Grid.AutoRefr eshTime	Numeri c/Integ er	Number of minutes after which the portal grids will auto refresh.	1 minute (default)	10.4
Portal.DefaultSolutionName	Text	Sets the default solution that will appear when user signs in to the portal.	Solution name	10.3.1

Key	Туре	Description	Value	Version
Portal.HideCoraOrchestrationSolu tion	Boolea n	Hides or shows the CoraOrchestration solution from the solution list in the portal.	 True - to show the CoraOrchestr ation solution in the list False (default) - to hide the CoraOrchestr ation solution 	10.3.1
Portal.Azure.ApplicationInsights.I nstrumentationKey	Text	Enables the user to connect to and use Azure Application Insights.	Instrumentation Key	10.3
Portal.Components.Grid.PageSize	Numeri c/Integ er	Enables the user to enter the full-screen mode in the portal to maximize the page view.	• 50 (default)	10.3
Portal.Forms.Conversations.IsMod al	Boolea n	Enables the user to access the case in the background.	• True • False	10.3
Portal.Components.Workflows.Ca tegories	Boolea n	Displays the categories on workflows page	True (default)False	10.2
Portal.Navigation.LastLocation	Boolea n	Enables the user to land in the portal on the same page where they left in their previous session.	True (default)False	10.2
Portal.Components.ToastNotificat ions.Duration	Numeri c/Integ er	Number of seconds for which the toast notification will last.	• 4 sec (default)	10.2
Portal.Session.SessionWarningCountdownTime	Numeri c/Integ er	Displays the session timeout warning in the set number of minutes before session timeout.	• n minutes	10.2

Key	Туре	Description	Value	Version
Portal.Links.ContactUs	Text	Adds Contact Us link to Flowtime	 URL of an external page path to Contact Us page in Cora SeQuence ~/SequenceForms/wf/WF Space/WFNa me/FormNa me/FormNa me/ViewNam e.ascx 	9.6-10.x
Portal.Links.PrivacyPolicy	Text	Adds Privacy Policy link to Flowtime	 URL of an external page Path to Privacy Policy page in Cora SeQuence ~/SequenceForms/wf/WF Space/WFNa me/FormNa me/ViewNam e.ascx 	9.6-10.x

Grid settings

Set the path to the customized tile view.

	Key	Туре	Description	Value	Version
--	-----	------	-------------	-------	---------

Кеу	Туре	Description	Value	Version
Portal.Grid.TileTemplate.SearchRe sults Portal.Grid.ExpandedTileTemplate .SearchResults	Text	Indicates the path to the custom layout of a collapsed/expanded tile in the search results grid. For details, see this article.	Path to the file location. For example, the path to the template of the Team Member grid: [rootfolder]\Cora SeQuence\Flowtime \Shared Resources\Compon ents\HotOperations \Flowtime\Templat es\TeamMember\M Ygrid-tile.html	9.2 - 10.x
Portal.Grid.TileTemplate.ProcessT asks Portal.Grid.ExpandedTileTemplate .ProcessTasks	Text	Indicates the path to the custom layout of a collapsed/expanded tile in the tasks page. For details, see this article.	Path to the file location. For example, the path to the template of the Team Member grid: [rootfolder]\Cora SeQuence\Flowtime \Shared Resources\Compon ents\HotOperations \Flowtime\Templat es\TeamMember\M Ygrid-tile.html	9.2 - 10.x
Portal.Grid.TileTemplate.ProcessInstances Portal.Grid.ExpandedTileTemplate .ProcessInstances	Text	Indicates the path to the custom layout of a collapsed/expanded tile in the process page tile view. NOTE For V10.x: Go to All Cases > Select a specific workflow template > Select tile view	Path to the file location	9.2 - 10.x
Portal.Grid.TileTemplate.UserInst ances Portal.Grid.ExpandedTileTemplate .UserInstances	Text	Indicates the path to the custom layout of a collapsed/expanded tile in the Cases I Started page tile view.	Path to the file location	9.2 - 10.x

Archive database

Initiate purging of the marked personal data while archiving.

Key	Туре	Description	Value	Version
JES.Archiving.PurgePiiDuringArch iving	Boolean	Initiates column purging of the marked personal data. For details, see this article.	 False: default, moves the personal data to the archive database. True: purges all the personal data columns while moving them to the archive database. 	9.7-9.x