

PowerShell Function: Set-CoraSeQuenceQuickSearchConfiguration

Last Modified on 07/16/2024 9:41 am EDT

V9.6

Module

CoraSeQuence

Description

Configures the Cora SeQuence Hot Operations case search capability.

Syntax

To enable the search feature:

```
Set-CoraSeQuenceQuickSearchConfiguration [-Enable] [-PageSize <Int32>] [-SiteID <Int32>] [<CommonParameters>]
```

To disable the search feature:

```
Set-CoraSeQuenceQuickSearchConfiguration [-Disable] [-SiteID <Int32>] [<CommonParameters>]
```

Parameters

-Enable [<SwitchParameter>]

Enables the case search capability.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

-PageSize <Int32>

Defines the number of results to display for search queries.

This parameter can be used with the `Enable` parameter or on its own.

Required?	false
Position?	named

Default value	0
Accept pipeline input?	false
Accept wildcard characters?	false

-Disable [<SwitchParameter>]

Disables the case search capability.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

-SiteID <Int32>

Sets the numeric ID of the site instance (for multiple instances of the same site).

Required?	false
Position?	named
Default value	1
Accept pipeline input?	false
Accept wildcard characters?	false

<CommonParameters>

This function supports these common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.

For more information, see [about_CommonParameters](#).

Examples

To enable search, use only the `Enable` parameter. If you want to limit the number of retrieved results, add the `PageSize` parameter.

```
PS C:\>Set-CoraSeQuenceQuickSearchConfiguration -Enable -PageSize 100
```

To disable search, use only the `Disable` parameter.

```
PS C:\>Set-CoraSeQuenceQuickSearchConfiguration -Disable
```

V9.2

Module

CoraSeQuence

Description

Configures the Cora SeQuence Hot Operations case search capability.

Syntax

To enable the search feature:

```
Set-CoraSeQuenceQuickSearchConfiguration [-Enable] [-PageSize <Int32>] [<CommonParameters>]
```

To disable the search feature:

```
Set-CoraSeQuenceQuickSearchConfiguration [-Disable] [<CommonParameters>]
```

Parameters

-Enable [**<SwitchParameter>**]

Enables the case search capability.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

-PageSize **<Int32>**

Defines the number of results to display for search queries.

This parameter can be used with the `Enable` parameter or on its own.

Required?	false
-----------	-------

Position?	named
Default value	0
Accept pipeline input?	false
Accept wildcard characters?	false

-Disable [<SwitchParameter>]

Disables the case search capability.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

<CommonParameters>

This function supports these common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.

For more information, see [about_CommonParameters](#).

Examples

To enable search, use only the `Enable` parameter. If you want to limit the number of retrieved results, add the `PageSize` parameter.

```
PS C:\>Set-CoraSeQuenceQuickSearchConfiguration -Enable -PageSize 100
```

To disable search, use only the `Disable` parameter.

```
PS C:\>Set-CoraSeQuenceQuickSearchConfiguration -Disable
```