

PowerShell Function: Set CoraSeQuenceSiteAuthentication

Last Modified on 01/12/2021 12:33 pm EST

V9.6

Method

CoraSeQuence.Sites

Description

Sets basic authentication types: Forms, Claims, or Windows, for a Cora SeQuence site.

Syntax

```
Set-CoraSeQuenceSiteAuthentication [-SiteType] [-AuthenticationType] [[-SiteID] ] [-AllInstances] [ ]
```

Parameters

-SiteType

Determines which Cora SeQuence site the deployed package is: Flowtime or Administration or WebAPI

.

Required?	true
Position?	1
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

-AuthenticationType

Defines the authentication type to set: Forms, Windows, or Claims (claims require additional manual configurations).

Required?	true
Position?	2
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

rs:

-SiteID

Sets the numeric ID of the site instance. Ignored if AllInstances is used.

Required?	false
Position?	3
Default value	1
Accept pipeline input?	false
Accept wildcard characters?	false

-AllInstances []

If provided, this parameter applies to all instances of the site provided in the SiteType parameter.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

This function supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.

For more information, see [about_CommonParameters](#).

Examples

```
PS C:\>Set-CoraSeQuenceSiteAuthentication -SiteType Administration -AuthenticationType Forms
```

```
PS C:\>Set-CoraSeQuenceSiteAuthentication -SiteType Flowtime -AuthenticationType Windows
```

Method

CoraSeQuence.Sites

Description

Sets basic authentication types: Forms, Claims, or Windows, for a Cora SeQuence site.

Syntax

```
Set-CoraSeQuenceSiteAuthentication [-SiteType] [-AuthenticationType] []
```

Parameters

-SiteType

Determines which Cora SeQuence site the deployed package is: Flowtime or Administration.

Required?	true
Position?	1
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

-AuthenticationType

Defines the authentication type to set: Forms, Windows, or Claims (claims requires additional manual configurations).

Required?	true
Position?	2
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

This function supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.

For more information, see [about_CommonParameters](#).

Examples

```
PS C:\>Set-CoraSeQuenceSiteAuthentication -SiteType Administration -AuthenticationType Forms
```

```
PS C:\>Set-CoraSeQuenceSiteAuthentication -SiteType Flowtime -AuthenticationType Windows
```