

PowerShell Function: Set-CoraSeQUENCESharedConfigurationLocation

Last Modified on 01/12/2021 12:33 pm EST

V9.6

Module

CoraSeQUENCE

Description

Sets a Cora SeQUENCE shared configuration location.

Syntax

```
Set-CoraSeQUENCESharedConfigurationLocation [-PhysicalPath ] -ApplicationType [-ApplicationID ] [-AllInstances] []
```

```
Set-CoraSeQUENCESharedConfigurationLocation -PhysicalPath []
```

Parameters

-PhysicalPath

The path to the central configuration folder.

Required?	false
Position?	named
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

-ApplicationType

Sets the configuration for a specific type of application. If not provided, configuration is set on all the installed apps.

Required?	true
Position?	named
Default value	
Accept pipeline input?	false

Accept wildcard characters?	false
-----------------------------	-------

-ApplicationID

The numeric ID for a specific instance of the application type to set. Ignored if AllInstances is used.

Required?	false
Position?	named
Default value	1
Accept pipeline input?	false
Accept wildcard characters?	false

-AllInstances []

Sets the configuration for all instances of the specified application.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

This command supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.

For more information, see [about_CommonParameters](#).

Example

```
PS C:\>Set-CoraSeQuenceSharedConfigurationLocation -DestinationPath "\\myserver\configurationfolder"
```

V9.1

Module

CoraSeQuence

Description

Sets a Cora SeQuence shared configuration location.

Syntax

```
Set-CoraSeQuenceSharedConfigurationLocation [-PhysicalPath] []
```

Parameters

-PhysicalPath

The path to the central configuration folder.

Required?	true
Position?	1
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

This command supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.

For more information, see [about_CommonParameters](#).

Example

```
PS C:\>Set-CoraSeQuenceSharedConfigurationLocation -DestinationPath "\\myserver\configurationfolder"
```