

PowerShell Function: Set-CoraSeQuenceDefaultFilesStorageConfiguration

Last Modified on 01/12/2021 12:30 pm EST

V9.6

Module

CoraSeQuence

Description

Sets the default file storage configuration for all the Cora SeQuence applications installed on the server, except ADSS.

Syntax

```
Set-CoraSeQuenceDefaultFilesStorageConfiguration -ConfigurationName -ApplicationType [-Applicati  
onID] [-AllInstances] []
```

```
Set-CoraSeQuenceDefaultFilesStorageConfiguration -ConfigurationName []
```

Parameters

-ConfigurationName

Sets the name of the file storage configuration. To restore the configuration to the Cora SeQuence SQL database, enter either "Default" or CoraSeQuence.Default.

Required?	true
Position?	named
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

-ApplicationType

Sets the configuration on a specific type of application. If not provided, configuration is set on all installed apps.

Required?	true
Position?	named
Default value	

Accept pipeline input?	false
Accept wildcard characters?	false

-ApplicationID

Sets the numeric ID for a specific instance of the application type to set. Ignored if AllInstances is used.

Required?	false
Position?	named
Default value	1
Accept pipeline input?	false
Accept wildcard characters?	false

-AllInstances

Sets the configuration on all instances of the specified application.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

This command supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.
For more information, see [about_CommonParameters](#).

Examples

```
PS C:\>Set-CoraSeQuenceDefaultFilesStorageConfiguration -ConfigurationName "AzureBlobStorage"
```

Module

CoraSeQuence

Description

Sets the default file storage configuration for all the Cora SeQuence applications installed on the server, except ADSS.

Syntax

```
Set-CoraSeQuenceDefaultFilesStorageConfiguration [-ConfigurationName] []
```

Parameters

-ConfigurationName

Sets the name of the file storage configuration. To restore the configuration to the Cora SeQuence SQL database, enter either "Default" or CoraSeQuence.Default.

Required?	true
Position?	1
Default value	
Accept pipeline input?	false
Accept wildcard characters?	false

This command supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable.
For more information, see [about_CommonParameters](#).

Examples

```
PS C:\>Set-CoraSeQuenceDefaultFilesStorageConfiguration -ConfigurationName "AzureBlobStorage"
```