

# OCR GetStatus

Last Modified on 09/28/2017 9:35 am EDT

Use the OCR GetStatus call to get the status of an [OCR FileBatch](#) process.

## Method

POST

## URL

[https://{Sequence.Server}/SequenceServices/coraOcrIntegration\\_v1.0.0.asmx](https://{Sequence.Server}/SequenceServices/coraOcrIntegration_v1.0.0.asmx)

## Response Codes

Responses follow standard [HTTP Status Codes](#).

## Input Parameters

The *MasterWorkflowInstanceId* is sent in the SOAP header. The *MasterWorkflowInstanceId* is the ID of the OCR workflow.

## Output Parameters

Name	Type	Description
Status	string	<ul style="list-style-type: none"><li>• Queued</li><li>• ProcessingInput</li><li>• WaitingForOutput</li><li>• Completed</li><li>• Aborted</li><li>• Failed</li><li>• NotFound</li></ul>
ErrorCode	string	<ul style="list-style-type: none"><li>• NoError</li><li>• TimedOut</li><li>• InputFileNotFound</li><li>• InputFileExists</li><li>• FailedToPutInputFile</li><li>• OutputFileExists</li><li>• FailedToPutOutputFile</li><li>• RobotProfileNotFound</li><li>• InternalError</li></ul>
ExternalContext	string	Additional process information.

## SOAP 1.1 Sample

### Request

```
POST /SequenceServices/coraOcrIntegration_v1.0.0.asmx HTTP/1.1
Host: admindev.pnmsoftlabs.com
Content-Type: text/xml; charset=utf-8
Content-Length: length
SOAPAction: "http://genpact.com/cora/orchestration/ocr/1.0.0/api/GetStatus"
```

```
guid
string
guid
string
long
guid
string
long
int
long
```

## Response

```
HTTP/1.1 200 OK
Content-Type: text/xml; charset=utf-8
Content-Length: length
```

```
Queued or ProcessingInput or WaitingForOutput or Completed or Aborted or Failed or No
Found
NoError or TimedOut or InputFileNotFound or InputFileExists or FailedToPutInputFile
OutputFileExists or FailedToPutOutputFile or RobotProfileNotFound or InternalError
string
```

## SOAP 1.2 Sample

### Request

```
POST /SequenceServices/coraOcrIntegration_v1.0.0.asmx HTTP/1.1
Host: admindev.pnmsoftlabs.com
Content-Type: application/soap+xml; charset=utf-8
Content-Length: length
```

```
guid
string
guid
string
long
guid
string
long
int
long
```

## Return

```
HTTP/1.1 200 OK
Content-Type: application/soap+xml; charset=utf-8
Content-Length: length
```

```
Queued or ProcessingInput or WaitingForOutput or Completed or Aborted or Failed or No
Found
NoError or TimedOut or InputFileNotFound or InputFileExists or FailedToPutInputFile o
OutputFileExists or FailedToPutOutputFile or RobotProfileNotFound or InternalError
string
```



## HTTP Sample

### HTTP GET

```
GET /SequenceServices/coraOcrIntegration_v1.0.0.asmx/GetStatus? HTTP/1.1
Host: admindev.pnmsoftlabs.com
```

```
HTTP/1.1 200 OK
Content-Type: text/xml; charset=utf-8
Content-Length: length
```

```
Queued or ProcessingInput or WaitingForOutput or Completed or Aborted or Failed or NotFound
NoError or TimedOut or InputFileNotFound or InputFileExists or FailedToPutInputFile or OutputFi
leExists or FailedToPutOutputFile or RobotProfileNotFound or InternalError
string
```

## HTTP POST

```
POST /SequenceServices/coraOcrIntegration_v1.0.0.asmx/GetStatus HTTP/1.1
Host: admindev.pnmsoftlabs.com
Content-Type: application/x-www-form-urlencoded
Content-Length: length
```

```
HTTP/1.1 200 OK
Content-Type: text/xml; charset=utf-8
Content-Length: length
```

```
Queued or ProcessingInput or WaitingForOutput or Completed or Aborted or Failed or NotFound
NoError or TimedOut or InputFileNotFound or InputFileExists or FailedToPutInputFile or OutputFi
leExists or FailedToPutOutputFile or RobotProfileNotFound or InternalError
string
```