

Cora SeSequence 8.6.2 Release Notes

Last Modified on 12/27/2018 6:41 am EST

11 October 2018

This is an update for Cora SeSequence v8.6, which includes product enhancements and resolved issues.

Product enhancements

- **Workflows with Built-in Command activities can now run in InMemory mode** InMemory mode provides faster response times and improved performance. It should be used for workflows that don't require saving data to the database.
- **Faster, easier, and more secure sign in with OpenID Connect:** Cora SeSequence now supports single sign-on authentication with the OpenID Connect protocol. This update requires changes to the Flowtime and Administration `web.config` files. For more details, see [Configure OpenID Connect authentication](#).
- **Enhanced SQL notification service:** Cora SeSequence components now use a new notification service. The change affects Administration and Flowtime `web.config` files and all other application configuration files.

New tag in the configuration files

```
...  
  
...  
PNMsoft.Sequence.Notifications.Sql.SqlServiceBrokerNotificationServiceFactory,  
PNMsoft.Sequence.Notifications.Sql, Version=8.0.0.0, Culture=neutral, PublicKeyToken=0a1a1b9  
0c1c5dca1" />
```

- **Cloud support (Preview):** Cora SeSequence is expanding its cloud capabilities. You can now install Cora SeSequence over Amazon Elastic Compute Cloud (Amazon EC2) and Amazon Relational Database Service (Amazon RDS) instances. See installation procedure below.

Resolved issues

- **Flowtime:** Changes made on the Administration > Analytics page were not displayed on Flowtime. (Ticket #56833)
- **App Studio:** File Writer activity that used tabs as field delimiters displayed differently on Process Lab and Flowtime. (Ticket #56209)
- **App Studio:** When you used the Split function to set up group or user expressions for task/message recipients, you got this error message: "Expression of type 'GroupView' expected," and could not continue setting up the workflow. (Ticket #55512)

Note: Ticket #55512 was solved in v8.6.1.1 and compiled into v8.6.2.

Update steps

Updating from v8.6.1

1. Back up the Cora SeSequence database.
2. Copy the JS files under **Shared Resources\Components\DataStreams\js** to a temporary location.
3. [Download](#) the ZIP file, and extract it.

4. Open the **DB Scripts** folder, and then run these scripts on your Cora SeSequence database in the following order:
 - a. `PatchSynchronization.sql`
 - b. `PatchSynchronization_Data.sql`
5. Run `SequencePatcher.ps1` file as Administrator on the Cora SeSequence Flowtime and Administration servers.
 - a. Right click `SequencePatcher.ps1` , and then select **Run with PowerShell**.

Rollback steps (in case of failure)

1. Restore the Cora SeSequence database to previous state.
2. Return the JS files.

Note: If you are running a Cora SeSequence version earlier than v8.6.1, you need to install v8.6.1 before you run the v8.6.2 update.

Install Cora SeSequence on AWS

Before you install Cora SeSequence v8.6.2 on AWS, you need to manually install version 8.6 with modified scripts.

Supported environment

- Windows Server 2016
- RDS with SQL Version 2017
- Single-server topology


Installation steps

The database needs to be installed separately using scripts before you run the installation wizard.

1. [Download](#) the V8.6 installation ZIP file, and extract it.
2. Locate the **First Installation** folder, and open the `1 - CreateDatabase.sql` file.
3. Delete the following lines:

```
EXEC dbo.sp_dbcmptlevel @dbname=N'Sequence', @new_cmptlevel=100  
  
GO
```

4. Save the file.
5. Resume the database installation, as described [here](#).
6. Run the Cora SeSequence v8.6 installation wizard, and in the Custom Setup screen, remove the **Database** feature.



7. Finish the installation wizard.
8. Perform the update steps for v8.6.1.
See [Cora SeSequence 8.6.1 Release Notes](#).
9. Perform the update steps for v8.6.2 (described above).

Heads up!

Cora SeSequence V8.8 will support Microsoft SQL Server 2014 SP1 and later only. Details to come in the next releases.