

Add a New Email Connection

Last Modified on 09/07/2022 8:13 am EDT

Starting with V10.0, Cora SeQUENCE has been renamed to Cora Orchestration.

V9.8.3-10.0

Overview

To send emails from Cora SeQUENCE to an email server, you need to set up a connection that uses the relevant email protocol: SMTP or Microsoft Graph.

Required parameters


Parameter	Description	For SMTP	For Microsoft Graph
Name	A unique connection name	Yes	Yes
Server	SMTP server name	Yes	No
Port	Server port	Yes	No
SSL	Establishes an SSL connection	Yes	No
Credential Name	Select a unique credential.	Select a Username Password type credential.	Select an OAuth2 Client Credentials type credential.

NOTE

It is recommended to create the required credentials before setting up the email connection. For details on creating a credential, see [this article](#).

Add connection

1. In the Administration site, go to **Administration > Global Settings > Email Sending Connections**.
2. Click **Add New Record**.



3. Select a connection type.



4. Based on the selected connection type, enter the required parameters.
5. To select a credential, click the ellipsis button.
6. On the Run As... screen, do one of the following:
 - Select one of the existing credentials, and then click **OK**.
 - If the list doesn't include the credential you need, to create a new one, click **Add**.
For more details, see [this article](#).
7. Click **Add**.

The new email sending connection is added to the list of connections and can be used when configuring email activities.

Previous to V9.8.3

Follow the steps to add a new SMTP connection for sending emails.

Select SMTP Connection

Select from the list, or Add New

Default
(default SMTP connection)

New...
Edit...
Delete
Refresh

Next Cancel

SMTP Connection Details

Name *

Server *

Port *
25 ← Default Port

Credential Name

SSL ← Selected by Default

OK Cancel

